

Black Viper's Windows 7 Service Pack 1 Service Configurations » Black Viper

www.blackviper.com

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	"Safe"	Tweak ed	Bare-b ones
ActiveX Installer (AxInstSV)	AxInstSV	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *
Adaptive Brightness	SensrSvc	Not Availab le	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *
Application Experience	AeLookupSvc	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Manual
Application Host Helper Service **	AppHostSvc	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
Application Identity	AppIDSvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Application Information	Appinfo	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual	Manual	Manual
Application Layer Gateway Service	ALG	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *
Application Managemen t	AppMgmt	Not Availab le	Not Availab le	Not Availab le	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *
ASP.NET State Service **	aspnet_state	Not Availab le	Not Availab le	Not Installe d (Manu al)	Not Installe d (Manu al)	Not Installe d (Manu al)	Not Installe d (Manu al)	Not Installe d	Not Installe d	Not Installe d
Background Intelligent Transfer Service	BITS	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *
Base Filtering Engine	BFE	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Disable d *

Display Name	Service Name (Registry)	DEFAULT Starter	DEFAULT Home Basic	DEFAULT Home Premium	DEFAULT Professional	DEFAULT Ultimate	DEFAULT Enterprise	“Safe”	Tweaked	Bare-bones
BitLocker Drive Encryption Service	BDESVC	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
Block Level Backup Engine Service	wbengine	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *
Bluetooth Support Service	bthserv	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *	Disabled *
BranchCache	PeerDistSvc	Not Available	Not Available	Not Available	Manual	Manual	Manual	Disabled *	Disabled *	Disabled *
Certificate Propagation	CertPropSvc	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *	Disabled *
Client for NFS **	NfsClnt	Not Available	Not Available	Not Available	Not Available	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed	Not Installed	Not Installed
CNG Key Isolation	KeyIso	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Disabled *
COM+ Event System	EventSystem	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic
COM+ System Application	COMSysApp	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Computer Browser	Browser	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Manual
Credential Manager	VaultSvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
Cryptographic Services	CryptSvc	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic
DCOM Server Process Launcher	DcomLaunch	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
Desktop Window Manager Session Manager	UxSms	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Disable d *
DHCP Client	Dhcp	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Diagnostic Policy Service	DPS	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Disable d *	Disable d *
Diagnostic Service Host	WdiServiceHost	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual	Disable d *	Disable d *
Diagnostic System Host	WdiSystemHost	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Disable d *	Disable d *
Disk Defragmenter	defragsvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Distributed Link Tracking Client	TrkWks	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Disable d *	Disable d *	Disable d *
Distributed Transaction Coordinator	MSDTC	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Manual
DNS Client	Dnscache	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Disable d *
Encrypting File System (EFS)	EFS	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *
Extensible Authentication Protocol	EapHost	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *
Fax **	Fax	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Uninst alled *
Function Discovery Provider Host	fdPHost	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual	Disable d *	Disable d *

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
Function Discovery Resource Publication	FDResPub	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Disable d *	Disable d *
Group Policy Client	gpsvc	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Health Key and Certificate Management	hkmsvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *
HomeGroup Listener	HomeGroup Listener	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Disable d *
HomeGroup Provider	HomeGroup Provider	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual	Manual	Disable d *
Human Interface Device Access	hidserv	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *
IIS Admin Service **	IISADMIN	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
IKE and AuthIP IPsec Keying Modules	IKEEXT	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *
Indexing Service **	CISVC	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Starte d, Autom atic)	Not Installe d	Not Installe d	Not Installe d
Interactive Services Detection	UIODetect	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *

Display Name	Service Name (Registry)	DEFAULT Starter	DEFAULT Home Basic	DEFAULT Home Premium	DEFAULT Professional	DEFAULT Ultimate	DEFAULT Enterprise	“Safe”	Tweaked	Bare-bones
Internet Connection Sharing (ICS)	SharedAccess	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled
IP Helper	iphlpvc	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Disabled *	Disabled *	Disabled *
IPsec Policy Agent	PolicyAgent	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *
KtmRm for Distributed Transaction Coordinator	KtmRm	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Link-Layer Topology Discovery Mapper	lltdsvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
LPD Service **	LPDSVC	Not Available	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed	Not Installed	Not Installed
Media Center Extender Service **	Mcx2Svc	Not Available	Not Available	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Uninstalled *
Message Queuing **	MSMQ	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed	Not Installed	Not Installed
Message Queuing Triggers **	MSMQTriggers	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed	Not Installed	Not Installed

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premium	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
Microsoft .NET Framework NGEN v2.0.50727	clr_optimizati on_v2.0.50727	Manual	Manual	Manual	Autom atic (Delay ed Start, Started	Manual	Autom atic (Delay ed Start, Started	Manual	Manual	Manual
Microsoft FTP Service **	ftpsvc	Not Availab le	Not Availab le	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
Microsoft iSCSI Initiator Service	MSiSCSI	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *
Microsoft Software Shadow Copy Provider	swprv	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Multimedia Class Scheduler	MMCSS	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Net.Msmq Listener Adapter **	NetMsmqAct ivator	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
Net.Pipe Listener Adapter **	NetPipeActiv ator	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
Net.Tcp Listener Adapter **	NetTcpActiv ator	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
Net.Tcp Port Sharing Service **	NetTcpPortS haring	Disable d	Disable d	Disable d	Disable d	Disable d	Disable d	Disable d	Disable d	Uninst alled *
Netlogon	Netlogon	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *
Network Access Protection Agent	napagent	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *
Network Connections	Netman	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual	Manual	Manual
Network List Service	netprofm	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual (Starte d)	Manual	Manual	Manual
Network Location Awareness	NlaSvc	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Network Store Interface Service	nsi	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Offline Files	CscService	Not Availab le	Not Availab le	Not Availab le	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Disable d *	Disable d *	Disable d *
Parental Controls	WPCSvc	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *
Peer Name Resolution Protocol	PNRPsvc	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Disable d *	Disable d *
Peer Networking Grouping	p2psvc	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Disable d *	Disable d *
Peer Networking Identity Manager	p2pimsvc	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Disable d *	Disable d *

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
Performanc e Logs & Alerts	pla	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Plug and Play	PlugPlay	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
PnP-X IP Bus Enumerator	IPBusEnum	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabl ed *	Disabl ed *
PNRP Machine Name Publication Service	PNRPAutoR eg	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabl ed *	Disabl ed *
Portable Device Enumerator Service	WPDBusEnu m	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Disabl ed *	Disabl ed *
Power	Power	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Print Spooler	Spooler	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Problem Reports and Solutions Control Panel Support	wercplsuppo rt	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabl ed *	Disabl ed *
Program Compatibilit y Assistant Service	PcaSvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabl ed *	Disabl ed *
Protected Storage	ProtectedSto rage	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Manual
Quality Windows Audio Video Experience	QWAVE	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabl ed *	Disabl ed *

Display Name	Service Name (Registry)	DEFAULT Starter	DEFAULT Home Basic	DEFAULT Home Premium	DEFAULT Professional	DEFAULT Ultimate	DEFAULT Enterprise	“Safe”	Tweaked	Bare-bones
Remote Access Auto Connection Manager	RasAuto	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Remote Access Connection Manager	RasMan	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Remote Desktop Configuration	SessionEnv	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled*	Disabled*
Remote Desktop Services	TermService	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled*	Disabled*
Remote Desktop Services UserMode Port Redirector	UmRdpService	Not Available	Not Available	Not Available	Manual	Manual	Manual	Manual	Disabled*	Disabled*
Remote Procedure Call (RPC)	RpcSs	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic
Remote Procedure Call (RPC) Locator	RpcLocator	Manual	Manual	Manual	Manual	Manual	Manual	Disabled*	Disabled*	Disabled*
Remote Registry	RemoteRegistry	Manual	Manual	Manual	Manual	Manual	Manual	Disabled*	Disabled*	Disabled*
RIP Listener**	iprip	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed (Automatic, Started)	Not Installed	Not Installed	Not Installed
Routing and Remote Access	RemoteAccess	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled	Disabled
RPC Endpoint Mapper	RpcEptMapper	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
SeaPort ***	SeaPort	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
Secondary Logon	seclogon	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Secure Socket Tunneling Protocol Service	SstpSvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *
Security Accounts Manager	SamSs	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Security Center	wscsvc	Autom atic (Delay ed Start, Started)	Autom atic (Delay ed Start, Started)	Autom atic (Delay ed Start, Started)	Autom atic (Delay ed Start, Started)	Autom atic (Delay ed Start, Started)	Autom atic (Delay ed Start, Started)	Autom atic (Delay ed Start)	Autom atic (Delay ed Start)	Disable d *
Server	LanmanServ er	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Shell Hardware Detection	ShellHWDet ection	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic (Starte d)	Autom atic	Autom atic	Autom atic
Simple TCP/IP Services **	simptcp	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
Smart Card	SCardSvr	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *
Smart Card Removal Policy	SCPolicySvc	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *	Disable d *

Display Name	Service Name (Registry)	DEFAULT Starter	DEFAULT Home Basic	DEFAULT Home Premium	DEFAULT Professional	DEFAULT Ultimate	DEFAULT Enterprise	“Safe”	Tweaked	Bare-bones
Telnet **	TIntSvr	Not Installed (Disabled)	Not Installed (Disabled)	Not Installed (Disabled)	Not Installed (Disabled)	Not Installed (Disabled)	Not Installed (Disabled)	Not Installed	Not Installed	Not Installed
Themes	Themes	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Disabled *
Thread Ordering Server	THREADORDER	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
TPM Base Services	TBS	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
UPnP Device Host	upnphost	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Manual
User Profile Service	ProfSvc	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic
Virtual Disk	vds	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Volume Shadow Copy	VSS	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Manual	Manual
Web Management Service **	WMSVC	Not Available	Not Available	Not Installed (Manual)	Not Installed (Manual)	Not Installed (Manual)	Not Installed (Manual)	Not Installed	Not Installed	Not Installed
WebClient	WebClient	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
Windows Audio	AudioSrv	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic
Windows Audio Endpoint Builder	AudioEndpointBuilder	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic
Windows Backup	SDRSVC	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Windows Biometric Service	WbioSrv	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
Windows CardSpace	idsvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Uninstalled *

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
Windows Process Activation Service **	WAS	Not Installed (Manual, Started)	Not Installed (Manual, Started)	Not Installed (Manual, Started)	Not Installed (Manual, Started)	Not Installed (Manual, Started)	Not Installed (Manual, Started)	Not Installed	Not Installed	Not Installed
Windows Remote Management (WS-Management)	WinRM	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *	Disabled *
Windows Search **	WSearch	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Disabled *	Disabled *	Uninstalled *
Windows Time	W32Time	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *
Windows Update	wuauclt	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start, Started)	Automatic (Delayed Start)	Automatic (Delayed Start)	Disabled *
WinHTTP Web Proxy Auto-Discovery Service	WinHttpAutoProxySvc	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual ****	Manual	Disabled *	Disabled *
Wired AutoConfig	dot3svc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *
WLAN AutoConfig	Wlansvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disabled *
WMI Performance Adapter	wmiApSrv	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Manual
Workstation	LanmanWorkstation	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic (Started)	Automatic	Automatic	Automatic

Display Name	Service Name (Registry)	DEFA ULT Starter	DEFA ULT Home Basic	DEFA ULT Home Premiu m	DEFA ULT Profes sional	DEFA ULT Ultimat e	DEFA ULT Enterpr ise	“Safe”	Tweak ed	Bare-b ones
World Wide Web Publishing Service **	W3SVC	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d (Autom atic, Started)	Not Installe d	Not Installe d	Not Installe d
WWAN AutoConfig	WwanSvc	Manual	Manual	Manual	Manual	Manual	Manual	Manual	Disable d *	Disable d *